




ວິທີຕັ້ງອີເມວຢູ່ MSOutlook

ໃນເວລາທີ່ບໍ່ຢູ່ຫ້ອງການຫຼືໄປຕ່າງປະເທດແຕ່ຕ້ອງການໂລດເບິ່ງອີເມວ prf.org ຂອງທ່ານ ສາມາດເບິ່ງໄດ້ຕາມວິທີດັ່ງລຸ່ມນີ້:
ກ່ອນອື່ນຕ້ອງເປີດ Microsoft Outlook ທີ່ມານຳ Microsoft Office ແລະ ເຮັດຕາມວິທີດັ່ງຮູບລຸ່ມນີ້:





Add New E-mail Account

Choose E-mail Service

Internet E-mail
Connect to your POP, IMAP, or HTTP server to send and receive e-mail messages.

Microsoft Exchange
Connect to Microsoft Exchange for access to your e-mail, calendar, contacts, faxes and voice mail.

Other
Connect to a server type shown below.

Outlook Mobile Service (Text Messaging)

< Back **Next >** Cancel

Add New E-mail Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information

Your Name: PRF Info

E-mail Address: info@prflaos.org

Server Information

Account Type: POP3

Incoming mail server: mail.prflaos.org

Outgoing mail server (SMTP): relay.prflaos.org

Logon Information

User Name: info

Password: *****

Remember password

Require logon using Secure Password Authentication (SPA)

Test Account Settings

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Test Account Settings ...

More Settings ...

< Back Next > Cancel

ໃສ່ຊື່ອີເມວຂອງທ່ານ

ໃສ່ username ແລະ password ຂອງອີເມວຂອງທ່ານ

Add New E-mail Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information

Your Name:

E-mail Address:

Server Information

Account Type:

Incoming mail server:

Outgoing mail server (SMTP):

Logon Information

User Name:

Password:

Remember password

Require logon using Secure Password Authentication (SPA)

Test Account Settings

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Internet E-mail Settings

Outgoing Server

My outgoing server (SMTP) requires authentication

Use same settings as my incoming mail server

Log on using

User Name:


Password:

Remember password

Require Secure Password Authentication (SPA)

Log on to incoming mail server before sending mail

ຄວນປະອືເມວໄວ້ໃນ Server ປະມານ 3 ມື້ກ່ອນຈຶ່ງໃຫ້ລຶບອອກຈາກ Server



ຖ້າບໍ່ເລືອກເອົາພາກສ່ວນນີ້ແມ່ນມັນຈະ ໂລດເອົາອີເມວທັງໝົດອອກມາໂດຍບໍ່ປະໄວ້ໃນ Server ເລີຍໃນເວລາຮັບອີເມວ